

Section 9

Data Set Creation — *Rocprep*

Distribution authorized to Sandia National Laboratories Personnel only (IllinoisRocstar Proprietary Information).
Other requests for this document shall be referred to IllinoisRocstar LLC (mdbrandy@illinoisrocstar.com)



Rocprep

Rocstar input data preparation tool

Rocstar/utilities/Rocprep

■ Native Data Archives

- Output from Gridgen, Patran, etc.
- Various grids (Grid1, Grid2, ...)
- Various module input/BC/control files (Data1, Data2, ...)
- README files

■ Tasks performed with a single command:


- Extract relevant files from archive
- Preprocess and partition for each module
- Construct overlay mesh for *Rocface*

■ Example: *Rocflo/Rocfrac* Lab Scale Rocket


```
% Rocprep -A -o 1 2 -f 1 3 -d /csar/NDAs/labscale -n 16
```




Anatomy of the Native Data Archive (NDA)




Rocflo NDA



Rocflu NDA



Rocfrac NDA



Rocprep Usage

Usage: rocprep -A|C|E|P [OPTION]...

Major modes of operation:

- A, --all extract and preprocess
- C, --check check an existing dataset at -d <path>
- E, --extract copy NDA files to target at -t <path>
- P, --preprocess run module preptools on data at -d <path>

Physics module selection:

- o [m] [n] Rocflo preprocessing, optional NDA Data<m> & Grid<n> dirs
- u [m] [n] Rocflu preprocessing, optional NDA Data<m> & Grid<n> dirs
- f [m] [n] Rocfrac preprocessing, optional NDA Data<m> & Grid<n> dirs
- s [m] [n] Rocsolid preprocessing, optional NDA Data<m> & Grid<n> dirs
- b Rocburn preprocessing

Module-specific flags:

- r <m> specify <m> regions (rocflu only), default is -n value
- splitaxis <n> force split along n=0,1, or 2 axis (rocflo only)
- un <units> convert model units to meters (rocfrac only)

General options:

- i <o|u|f|s> surfdiver interface meshes, default infers from physics options
- d <path> path to source data, default is current working directory
- h, --help print this help message and terminate
- n <m> specify <m> processors/partitions
- t <path> target path for new rocstar dataset
- p <path> path to preptool binaries, default will use shell path
- x, --ignore ignore RocprepControl.txt control file

Example: rocprep -A -o 1 1 -f 2 4 -b -d archiveDir/ -t newDataset/ -n 8