


Section 15: Use Case 2

Attitude Control Motor - Rocflu



Problem Description

- Small (2 inch) Attitude Control Motor (ACM)
- Regressing burning surface
- Fluid-combustion coupling
- Rocflu model – unstructured tetrahedral grid
- Goal: assemble and run moving-boundary fluid-combustion coupled run with Rocflo



File Checklist

■ Rocstar

- RocstarControl.txt

■ Rocman

- RocmanControl.txt

■ RocburnAPN

- RocburnAPNControl.txt

■ Rocflu


- RocfluControl.txt
- ACM.inp
- ACM.bc
- ACM.cgi
- ACM-COBALT.bc
- ACM-COBALT.inp

Preparing *Rocflu* Input

Outline

- Produce CAD model
 - Pro/Engineer exports IGES format
 - Can make simple geometries in Gridgen
 - Generate meshes, set BC flags
 - Gridgen – unstructured mixed meshes for *Rocflu*
 - Tets, hexes, prisms, pyramids
-
- Set up NDA with grids and input files
 - Choose a “casename”; ACM for this example
 - Grid, boundary condition map file
 - Basic input, boundary conditions, control files
 - Preprocess and partition
 - Use *Rocprep* on NDA
 - Check input again!

Cutaway of Partitioned Model



Rocflu Boundary Conditions

- Make sure Analysis Software is set to COBALT
 - Can't fix after setting BCs!
- Make sure all external surfaces have a BC
- BC labels not that important for COBALT – will map to patches through the <casename>.cgi file
- Using all custom BC's is advisable for bookkeeping purposes
- Separate BC for each physical bc/motion constraint pair

COBALT BCs	
Create Custom BC	c
No Boundary Condition	0
Farfield	1
Sink	2
Source	3
Solid Wall	4
Periodic - Side 1	5
Periodic - Side 2	6
User Specified	7
SlideInXAftEnd	9
HeadEndSolidSurface	10
SlideInXHeadEnd	11
NozzleSurface	12
ErodingNozzle	13
Abort	esc
Help	?



SELECT ANALYSIS S/W			
Prev Page	L	Next Page	R
◇ 2D	a	◆ 3D	b
◇ generic			0
◇ ADPAC			1
◇ ANSYS CFX			2
◇ CFDSHIP-IOWA			3
◇ CFD++			4
◇ CFX-4			5
◇ CGNS-Struct			6
◇ CGNS-Unstr			7
◇ CNSFV			8
◆ COBALT			9
◇ COMO			^0
◇ CRUNCH			^1
◇ DTNS			^2
◇ EXODUS II			^3
◇ FALCON v3			^4
◇ FANS			^5
◇ FDNS/UNIC			^6
◇ FLUENT v4			^7
◇ FLUENT			^8
◇ FrontFlow			^9






Export Rocflu Grid

■ Export files:

- COBALT mesh: <casename>-COBALT.inp – example: ACM-COBALT.inp
- BC file <casename>-COBALT.bc – example: ACM-COBALT.bc

■ If working on Windows, run dos2unix on them once on Linux


- Fortran doesn't like cross-platform line endings



Set filenames as
 <casename>-COBALT
 Extensions are automatic



Examine NDA



Run *Rocprep* on NDA

rocprep -A -u 1 1 -b -d /IR/NDAs/ACM -t ./ACM16 -n 16 [-p ~/build/bin/]

**Extract from
NDA and
preprocess to
make full
Rocstar dataset**

**Process Data1
and Grid1
for Rocflu**

**Root directory
for NDA problem
to be processed**

**Extract
Rocburn**

**Target dir for
dataset**

**Number of
partitions to
make**

**Optional
path to pre-
processing
tools**

**Execute *Rocprep*
with no arguments
for help screen:**

```
[mdblrandy@taubh1 Modin]$ ~/Rocprep/Rocprep.pm
First switch must be mode switch -A|C|E|P|U, not:

*****
Usage: /home/mdblrandy/Rocprep/Rocprep.pm -A|C|E|P [OPTION]...

Major modes of operation:
-A, --all          extract and preprocess
-C, --check        check an existing dataset at -d <path>
-E, --extract      copy NDA files to target at -t <path>
-P, --preprocess   run module preptools on data at -d <path>


Physics module selection:
-o [m] [n]         Rocflo preprocessing, optional NDA Data<m> & Grid<n> dirs
-u [m] [n]         Rocflu preprocessing, optional NDA Data<m> & Grid<n> dirs
-f [m] [n]         Rocfrac preprocessing, optional NDA Data<m> & Grid<n> dirs
-s [m] [n]         Rocsolid preprocessing, optional NDA Data<m> & Grid<n> dirs
-b                 Rocburn preprocessing

Module-specific flags:
-r <m>              specify <m> regions (rocflu only), default is -n value
-splitaxis <n>     force split along n=0,1, or 2 axis (rocflu only)
-un <units>         convert model units to meters (rocfrac only)

General options:
-i <o|u|f|s>        surfdive interface meshes, default infers from physics options
-d <path>           path to source data, default is current working directory
-h, --help          print this help message and terminate
-n <m>              specify <m> processors/partitions
-t <path>           target path for new rocstar dataset
-p <path>           path to preptool binaries, default will use shell path
-x, --ignore        ignore RocprepControl.txt control file
```

```
Example: /home/mdblrandy/Rocprep/Rocprep.pm -A -o 1 1 -f 2 4 -d archiveDir/ -t newDataset/ -n 8
*****
```


Resulting Rocstar Dataset



**There will be several sets of files with names containing com, dim, rnm, and cmp that are internal *Rocflu* files that are not generally examined

ACM.bc file

```
# BC_INJECT
PATCH      1 1
NAME        InjectionWall
MFRATE      5.7429
TEMP        2855.0
RFVFU       0.0
RFVFW       0.0
RFVFW       0.0
COUPLED     1
BFLAG       1
MOVEDIR     7
#

# BC_SLIPW
PATCH      2 2
NAME        AftFlatWall
COUPLED     2
MOVEDIR     0
#

# BC_SLIPW
PATCH      3 3
NAME        HeadEndSurface
COUPLED     2
MOVEDIR     0
#

# BC_OUTFLOW
PATCH      4 4
NAME        NozzleOutlet
TYPE        0
COUPLED     2
MVPATCH     0
SMGRID      0
CORR        0
MOVEDIR     0
#
```

```
# BC_SLIPW
PATCH      5 5
NAME        HeadEndRing
COUPLED     2
MOVEDIR     1
#

# BC_SLIPW
PATCH      6 6
NAME        AftEndRing
COUPLED     2
MOVEDIR     1
#

# BC_SLIPW
PATCH      7 7
NAME        NozzleSurface
COUPLED     2
MOVEDIR     0
#


# END
```

- Rocflu BCs are defined by "patch"
- Patches correspond to Gridgen BC definitions on specific sections of the model



ACM.cgi

- File maps Gridgen BC numbers to Rocflu .bc BC definitions
- Same function as Rocflo <casename>.bcmap file




```
#####
Boundary Condition Specification File for:
Gridgen grid exported : Wed Feb 27 14:06:19 2008
#####
11
Gridgen bc region: 11
SlideInXHeadEnd
Methods: User Created BC
User data supplied here - see COBALt doc!
#####
10
Gridgen bc region: 10
HeadEndSolidSurface
Methods: User Created BC
User data supplied here - see COBALt doc!
#####

...
2
Gridgen bc region: 2
Sink
Methods: Static Pressure, Mass Flow, Corrected Mass
Flow, Bleed Plenum Pressure, Area Ratio
Value      Porosity
User data supplied here - see COBALt doc!
No
#####
```



Examine RocfluControl.txt



- Note: Casename is critical. It is used for *Rocprep* and *Rocflu* to know what other files are called. Make sure it is used consistently.
- Normally the other lines will always be the same



Physics Module Files: *Rocflu* (I)

labscale.inp

```
# NUMERICS
CFL      3.0      ! CFL number
DISCR    3        ! Type of space discretization (1 - Roe, 2 - MAPS)
ORDER    2        ! Order of accuracy (1 - first, 2 - second)
#
# TIMESTEP
FLOWTYPE 1        ! 0 - steady flow, 1 - unsteady flow
PRNTIME  0.000001 ! Offset between iterations to print convergence
DTMINLIMIT 5.0E-09
#
# REFERENCE
GAMMA    1.2444
CP       1905.0
#
# PROBE
NUMBER 2
0.001 0.0 0.0
0.0495735 0.0 0.0
#
WRITIME 0.00001
OPENCLOSE 1
#
#
```

Must be 2 while preprocessing for moving geometries



Physics Module Files: *Rocflu* (II)

```
# TRANSFORM
FLAG      1
SCALE_X    0.0254
SCALE_Y    0.0254
SCALE_Z    0.0254
#
# ROCKET    ! Analytic Description of Rocket Case
CASERAD    0.446532
COORDL     1.0
ELLIPSL    0.239268
HEADEND    0.0
AFTEND     -7.0
#
# TIMEZOOMING ! Planar limits for TimeZooming
MAXPLANE   -0.022
MINPLANE   -4.261
AXIS       1.0
#
```



Examine *Rocstar* Control Files for ACM

RocstarControl.txt

```

CouplingScheme      = FluidBurnAlone
FluidModule         = "Rocflu"
BurnModule          = "RocburnAPN"
OutputModule        = "Rocout"

MaximumTime         = 0.016
AutoRestart         = T
CurrentTimeStep     = 1.0E-06
OutputIntervalTime = 1.0E-04
ZoomFactor          = 1.0

MaxWallTime         = 43000

ProfileDir          = "Rocman/Profiles"
  
```

RocmanControl.txt

```

Verbose = 0

InterpolationOrder = 1

TractionMode = 1
P_ambient = 1.0E+05

Rhoc = 1703.0
Pressure = 6.8d6
BurnRate = 0.01

RFC_verb = 1
RFC_order = 2
RFC_iteration = 100
RFC_tolerance = 1.e-6

Face-offsetting = T
  
```

Important

Must be 1.0 to allow
boundary regression



RocburnAPN for ACM

Careful with units when setting

```
0.77      a in rb=a*P^n,  rb in cm/sec and P in atm, a_p (cm/sec)
0.62      n in rb=a*P^n,  rb in cm/sec and P in atm, n_p
1         Maximum_number_of_spatial_nodes, nymax
2916.0    adiabatic flame temperature, Tf_adiabatic (K)
298.00    initial temperature          , To_read      (K)
Rocburn_2D_Output/Rocburn_APN
```

- Burn rate is one of the only places in *Rocstar* that is not strictly SI units (meters)



Run ACM problem

```
#!/bin/csh -f

#SBATCH --nodes=2                # Number of nodes
#SBATCH --time=10:00:00          # Wall clock time
#SBATCH --account=FY127542      # WC ID
#SBATCH --job-name=ACMTest      # Name of job
set nodes=$SLURM_JOB_NUM_NODES
set cores=8
cd /gscratch2/aluketa/ACMTest
srun -n 16 /projects/Rocstar/Rocstar/bin/rocstar
```

- Need to set up a batch-system specific job script for your system.
- Example below for our system for ACM

```
#!/bin/tcsh
#
# Request 2 nodes, 8 procs each (i.e. 16 procs)
#PBS -l nodes=2:ppn=8
# For this long:
#PBS -l walltime=10:00:00
#
# Send me a mail when my job starts and ends
#PBS -m be
# To this address
#PBS -M mdbrandy@illinoisrocstar.com
# with this jobname
#PBS -N ACM
# Join the stdout and stderr into the output file
#PBS -j oe

# cd to the directory from which the job was submitted
cd ${PBS_O_WORKDIR}
mpirun -np 16 ./rocstar
```



Monitor Standard out/err

- Large amounts of information is written to standard out/err



Monitor Probe File(s)

- Depending upon your setup, you can “watch” the probe files to monitor progress
- `cd Rocflu/Modout; tail -f ACM.prb_0001`


```
# probe data (iteration/time, density, u, v, w, p, T)
# region      14, icell      3, jcell      9, kcell      9
# x= 0.14856E-01, y= 0.21521E-07, z= -0.14945E-07
2.7035969E-07 1.16000E+00 -1.06085E-14 -4.21347E-14 2.29825E-14 1.00000E+05 2.45467E+02
5.0000000E-06 1.18107E+00 -4.35562E-02 -1.10686E-03 -1.55134E-03 1.02232E+05 2.46470E+02
1.0000000E-05 2.60138E+00 -2.43497E+01 -2.06613E-03 -6.09490E-03 2.73136E+05 2.98969E+02
1.5000000E-05 2.21299E+00 -2.76699E+01 -9.98801E-03 3.66079E-02 2.24079E+05 2.88318E+02
2.0000000E-05 3.72242E+00 -7.31183E+01 8.72279E-03 -2.65008E-02 4.25827E+05 3.25730E+02
2.5000000E-05 4.24793E+00 -1.10089E+02 1.99342E-02 9.96979E-03 5.02469E+05 3.36808E+02
3.0000000E-05 4.82351E+00 -1.38443E+02 -3.53893E-02 -7.66165E-02 5.87183E+05 3.46625E+02
3.5000000E-05 3.51547E+00 -1.72720E+02 1.88846E-02 4.85104E-02 3.98075E+05 3.22427E+02
4.0000000E-05 4.88654E+00 -1.98719E+02 -9.84630E-03 -2.71287E-02 5.96106E+05 3.47354E+02
4.5000000E-05 5.91230E+00 -1.71383E+02 -1.23496E-02 -4.90376E-02 7.56641E+05 3.64404E+02
5.0000000E-05 4.86712E+00 -1.91427E+02 2.05179E-03 5.82279E-02 5.95716E+05 3.48512E+02
5.5000000E-05 6.42790E+00 -1.81320E+02 9.75009E-03 -2.17876E-02 8.41403E+05 3.72722E+02
6.0000000E-05 1.19800E+01 -1.42908E+02 -4.73421E-02 -2.96886E-02 1.83861E+06 4.37002E+02
6.5000000E-05 1.30104E+01 -1.60689E+02 -2.81673E-02 9.27011E-03 2.05774E+06 4.50351E+02
7.0000000E-05 9.95572E+00 -1.67150E+02 4.40584E-03 1.54315E-02 1.52269E+06 4.35500E+02
7.5000000E-05 1.05171E+01 -1.55261E+02 -5.44063E-02 -1.11832E-04 1.71412E+06 4.64082E+02
8.0000000E-05 1.45618E+01 -1.37359E+02 -1.81264E-02 -2.33013E-02 2.67457E+06 5.22986E+02
```

- The location of this probe is defined in ACM.inp

```
# PROBE
NUMBER 2
0 0.015 0.0 0.0
0 0.0495735 0.0 0.0
#
```



Head End Pressure Probe



Visualize HDF Output

- Can use Rocketeer to visualize output
- Can also translate to Tecplot format
- Need to learn to read output file naming
- `cd Rocflu/Rocout; ls`
- Once a checkpoint has occurred, there will be one HDF file per processor per checkpoint
- Example:

● `fluid_06.100000_0000.hdf`: processor 0, 0.10ms time

Means 0.10E06 nanoseconds,
Or 0.10 ms, or 0.0001 seconds

- `fluid_xx.xxxxxx_xxx.hdf` are 3-D volume grid files
- `ifluid_Y_xx.xxxxxx_xxxx.hdf` are surface grid files
 - Y: ni=non-interacting, b=burning



Pre-run Visualization Files

- For Rocflu ACM, pre-run visualization files are available for 0ms, 5 ms, 10 ms, 14 ms
- Load these into Rocketeer from the VizData directory

